

# ROS Localization

---

WeGo & Logistics Robot

# 목 차

1. Localization Introduction
2. Localization Package
3. Localization Demo


**01**

---

## **Localization Introduction**



# 01 Localization Introduction

- Navigation은 Mobile Robot 관점에서 핵심적인 기능 중 하나입니다.
- Navigation을 위해서는 로봇의 현재 위치를 파악하는 것이 중요합니다.
- 주어진 지도 상에서 로봇의 현재 위치를 파악하는 기술을 Localization(지역화) 기술이라고 합니다. 또는 위치 추정(Position Estimation)이라고도 합니다.



# 01 Localization Introduction

- 로봇의 형태 및 자유도에 따라서 추정해야하는 차원 수가 달라집니다.
- 일반적인 2D 환경에서 이동하는 Mobile Robot의 경우는 지도 상에서의 위치( $x, y$ ) 및 헤딩 각( $\theta$ )의 세 가지 정보를 Pose  $x_t = (x, y, \theta)^T$  와 같이 표시한다.
- 사용하는 센서로는 내부의 이동을 측정하는 Odometer (주행 기록계) 및 LiDAR 센서 데이터를 두 가지를 사용한다.



# 01 Localization Introduction


- Differential Drive Model

$$\begin{aligned}\dot{x} &= \frac{r}{2}(v_l + v_r)\cos(\theta) \\ \dot{y} &= \frac{r}{2}(v_l + v_r)\sin(\theta) \\ \dot{\theta} &= \frac{r}{L}(v_r - v_l)\end{aligned}$$

$$\begin{aligned}\dot{x} &= v\cos(\phi) \\ \dot{y} &= v\sin(\phi) \\ \dot{\phi} &= \omega\end{aligned}$$



(a)



(b)


# 01 Localization Introduction

- Differential Drive Model

$$v = \frac{R}{2} (v_r + v_l)$$
$$\omega = \frac{R}{L} (v_r - v_l)$$



(a)




(b)

# 01 Localization Introduction

- Mobile Robot Localization Graphical Model

- Robot State  $x_{t-1}$
- Map Data  $m$
- Measurement (LiDAR)  $z_{t-1}$
- Control Data (Odometry)  $u_{t-1}$





# 01 Localization Introduction

- Position Tracking - 로봇의 초기 위치를 알고 있고, 이를 기반으로 로봇의 움직임을 추적하여, 로봇의 위치를 추정하는 방법 (Local Problem)
- Global Localization - 로봇의 초기 위치를 모르는 상태이며, 지도 상의 한 점에서 시작을 하지만 위치는 알 수 없는 상태(Global Problem)





Image source: John-Olof Nilsson, Amit K.Gupta, Peter Handel, "Foot mounted inertial navigation made easy", Proc. Indoor Positioning & Indoor Navigation (IPIN), 2014


# 01 Localization Introduction

- Monte Carlo Localization(Particle Filter)
  - 전체 지도에서 균일하게 확률 분포를 생성한다.
  - 로봇의 센서를 통해 주변 환경을 확인하고 확률 분포를 업데이트한다.
  - 로봇을 이동시키고, 로봇의 이동한 값을 이용하여 확률 분포를 업데이트한다.
  - 2 ~ 3의 과정을 반복하여 수렴시킨다.

# 01 Localization Introduction



# 01 Localization Introduction



02

---

## Localization Package

## 02 Localization Package

- **amcl** - adaptive monte carlo localization
- **Published Topics**
  - **amcl\_pose** (geometry\_msgs/PoseWithCovarianceStamped) - Robot's estimated pose in the map, with covariance.
  - **particlecloud** (geometry\_msgs/PoseArray) - The set of pose estimates being maintained by the filter.
  - **tf** (tf/tfMessage) - Publishes the transform from odom (~odom\_frame\_id parameter) to map.
- **Subscribed Topics**
  - **scan** (sensor\_msgs/LaserScan) - Lidar Laser scan data.
  - **tf** (tf/tfMessage) - Transforms.
  - **initialpose** (geometry\_msgs/PoseWithCovarianceStamped) - Mean and covariance with which to (re-)initialize the PF.
  - **map** (nav\_msgs/OccupancyGrid) - When the use\_map\_topic parameter is set, AMCL subscribes to map topic to retrieve the map used for laser-based localization

## 02 Localization Package

- **Parameters(Default) – Overall filter parameters**
  - `~min_particles` (100) – Minimum allowed number of particles.
  - `~max_particles` (5000) – Maximum allowed number of particles.
  - `~kld_err` (0.01) – Maximum error between the true distribution and the estimated distribution.
  - `~kld_z` (0.99) – Upper standard normal quantile for  $(1 - p)$ , where  $p$  is the probability that the error on the estimated distribution will be less than `kld_err`.
  - `~update_min_d` (0.2 meters) – Translational movement required before performing a filter update.
  - `~update_min_a` ( $\pi/6.0$  radians) – Rotational movement required before performing a filter update.
  - `~resample_interval` (2) – Number of filter updates required before resampling.
  - `~transform_tolerance` (0.1 seconds) – Time with which to post-date the transform that is published, to indicate that this transform is valid into the future.
  - `~recovery_alpha_slow` (0.0 (disabled)) – Exponential decay rate for the slow average weight filter, used in deciding when to recover by adding random poses. A good value might be 0.001.
  - `~recovery_alpha_fast` (0.0 (disabled)) – Exponential decay rate for the fast average weight filter, used in deciding when to recover by adding random poses. A good value might be 0.1.
  - `~initial_pose_x` (0.0 meters) – Initial pose mean (x), used to initialize filter with Gaussian distribution.
  - `~initial_pose_y` (0.0 meters) – Initial pose mean (y), used to initialize filter with Gaussian distribution.
  - `~initial_pose_a` (0.0 radians) – Initial pose mean (yaw), used to initialize filter with Gaussian distribution.

## 02 Localization Package

- **Parameters(Default) - Overall filter parameters**
  - `~initial_cov_xx` (0.5\*0.5 meters) - Initial pose covariance (x\*x), used to initialize filter with Gaussian distribution.
  - `~initial_cov_yy` (0.5\*0.5 meters) - Initial pose covariance (y\*y), used to initialize filter with Gaussian distribution.
  - `~initial_cov_aa` ( $(\pi/12)*(\pi/12)$  radian) - Initial pose covariance (yaw\*yaw), used to initialize filter with Gaussian distribution.
  - `~gui_publish_rate` (double, default: -1.0 Hz) - Maximum rate (Hz) at which scans and paths are published for visualization, -1.0 to disable.
  - `~save_pose_rate` (double, default: 0.5 Hz) - Maximum rate (Hz) at which to store the last estimated pose and covariance to the parameter server, in the variables `~initial_pose_*` and `~initial_cov_*`. This saved pose will be used on subsequent runs to initialize the filter, -1.0 to disable.
  - `~use_map_topic` (bool, default: false) - When set to true, AMCL will subscribe to the map topic rather than making a service call to receive its map. New in navigation 1.4.2
  - `~first_map_only` (bool, default: false) - When set to true, AMCL will only use the first map it subscribes to, rather than updating each time a new one is received. New in navigation 1.4.2
  - `~selective_resampling` (bool, default: false) - When set to true, will reduce the resampling rate when not needed and help avoid particle deprivation. The resampling will only happen if the effective number of particles ( $N_{eff} = 1/(\sum(k_i^2))$ ) is lower than half the current number of particles. Reference: Grisetti, Giorgio, Cyrill Stachniss, and Wolfram Burgard. "Improved techniques for grid mapping with rao-blackwellized particle filters." IEEE transactions on Robotics 23.1 (2007): 34.



## 02 Localization Package

- **Parameters(Default) - Laser model parameters**
  - `~laser_min_range (-1.0)` - Minimum scan range to be considered, -1.0 will cause the laser's reported minimum range to be used.
  - `~laser_max_range (-1.0)` - Maximum scan range to be considered; -1.0 will cause the laser's reported maximum range to be used.
  - `~laser_max_beams (30)` - How many evenly-spaced beams in each scan to be used when updating the filter.
  - `~laser_z_hit (0.95)` - Mixture weight for the `z_hit` part of the model.
  - `~laser_z_short (0.1)` - Mixture weight for the `z_short` part of the model.
  - `~laser_z_max (0.05)` - Mixture weight for the `z_max` part of the model.
  - `~laser_z_rand (0.05)` - Mixture weight for the `z_rand` part of the model.
  - `~laser_sigma_hit (0.2 meters)` - Standard deviation for Gaussian model used in `z_hit` part of the model.
  - `~laser_lambda_short (0.1)` - Exponential decay parameter for `z_short` part of model.
  - `~laser_likelihood_max_dist (2.0 meters)` - Maximum distance to do obstacle inflation on map, for use in `likelihood_field` model.
  - `~laser_model_type ("likelihood_field")` - Which model to use, either `beam`, `likelihood_field`, or `likelihood_field_prob` (same as `likelihood_field` but incorporates the `beamskip` feature, if enabled).

## 02 Localization Package

- **Parameters(Default) – Odometry model parameters**
  - `~odom_model_type` ("diff") – Which model to use, either "diff", "omni", "diff-corrected" or "omni-corrected".
  - `~odom_alpha1` (0.2) – Specifies the expected noise in odometry's rotation estimate from rotational component of robot's motion.
  - `~odom_alpha2` (0.2) – Specifies the expected noise in odometry's rotation estimate from translational component of robot's motion.
  - `~odom_alpha3` (0.2) – Specifies the expected noise in odometry's translation estimate from translational component of robot's motion.
  - `~odom_alpha4` (0.2) – Specifies the expected noise in odometry's translation estimate from the rotational component of robot's motion.
  - `~odom_alpha5` (0.2) – Translation-related noise parameter (only used if model is "omni").
  - `~odom_frame_id` ("odom") – Which frame to use for odometry.
  - `~base_frame_id` ("base\_link") – Which frame to use for the robot base
  - `~global_frame_id` ("map") – The name of the coordinate frame published by the localization system
  - `~tf_broadcast` (true) – Set this to false to prevent amcl from publishing the transform between the global frame and the odometry frame.

## 02 Localization Package

- particle filter – basic particle filter localization
- Published Topics
  - `/pf/pose/odom` (`nav_msgs/Odometry`) – Robot's estimated pose in the map, with covariance.
  - `/pf/viz/fake_scan` (`sensor_msgs/LaserScan`) – Fake Scan made from Map
  - `/pf/viz/inferred_pose` (`geometry_msgs/PoseStamped`) – Robot's estimated pose in the map
  - `/pf/viz/particles` (`geometry_msgs/PoseArray`) – Particle's position
- Subscribed Topics
  - `/initialpose` (`geometry_msgs/PoseWithCovarianceStamped`) – Recover Position
  - `/scan` (`sensor_msgs/LaserScan`) – 2D LiDAR Range Data
  - `/vesc/odom` (`nav_msgs/Odometry`) – Odometry of Vehicle

## 02 Localization Package

- Parameters
  - ~angle\_step
  - ~fine\_timing
  - ~max\_particles
  - ~max\_range
  - ~max\_viz\_particles
  - ~motion\_dispersion\_theta
  - ~motion\_dispersion\_x
  - ~motion\_dispersion\_y
  - ~odometry\_topic
  - ~publish\_odom
  - ~range\_method
  - ~rangelib\_variant
  - ~scan\_topic
  - ~sigma\_hit
  - ~squash\_factor
  - ~theta\_discretization
  - ~viz
  - ~z\_hit
  - ~z\_max
  - ~z\_rand
  - ~z\_short

**03**

---

## **Localization Demo**

## 03 Localization Demo


- amcl - adaptive monte carlo localization
  - Particle Filter 기반의 Localization 방법
  - Input : 플랫폼의 이동에 해당하는 Odometry, 2D LiDAR 거리 데이터
  - GMapping 또는 Hector SLAM을 통해서 생성한 Map 상의 로봇의 위치를 추정
  - Odometry의 정확도에 많이 의존하는 편이며, LiDAR를 이용하는 모든 알고리즘과 유사하게 직선 주행에서는 괜찮으나, 회전에서 많이 취약한 편
  - 수동으로 위치를 보정하는 기능 및 Global Localization 두 가지 방법을 모두 제공

## 03 Localization Demo

- amcl – adaptive monte carlo localization
- AMCL ROS Wiki – <http://wiki.ros.org/amcl>
- AMCL Github – <https://github.com/ros-planning/navigation>
- Related Papers
  - KLD-Sampling: Adaptive Particle Filters –  
<https://proceedings.neurips.cc/paper/2001/file/c5b2cebf15b205503560c4e8e6d1ea78-Paper.pdf>
  - <https://roboticsknowledgebase.com/wiki/state-estimation/adaptive-monte-carlo-localization/>

## 03 Localization Demo

- amcl – adaptive monte carlo localization
  - `$ roslaunch wecar teleop.launch`
  - `$ roscd wecar/map`
  - `$ rosrun map_server map_server "FILENAME.YAML"`
  - `$ roslaunch amcl amcl_diff.launch`





## 03 Localization Demo


- particle filter - basic particle filter package
  - Particle Filter 기반의 Localization 방법
  - Input : 플랫폼의 이동에 해당하는 Odometry, 2D LiDAR 거리 데이터
  - GMapping 또는 Hector SLAM을 통해서 생성한 Map 상의 로봇의 위치를 추정
  - AMCL에 비해 수정 가능성 및 자유도가 높은편이지만, 기본 성능 자체가 많이 낮은편

## 03 Localization Demo

- particle filter - basic particle filter localization
- particle filter Github - [https://github.com/mit-racecar/particle\\_filter](https://github.com/mit-racecar/particle_filter)
- Related Papers
  - Lab5-Localization&Mapping -  
[https://github.com/mit-racecar/particle\\_filter/blob/master/docs/Lab5.pdf](https://github.com/mit-racecar/particle_filter/blob/master/docs/Lab5.pdf)
  - RangeLibC Usage and Information -  
[https://github.com/mit-racecar/particle\\_filter/blob/master/docs/RangeLibcUsageandInformation.pdf](https://github.com/mit-racecar/particle_filter/blob/master/docs/RangeLibcUsageandInformation.pdf)

## 03 Localization Demo

- particle filter – basic particle filter localization
  - `$ roslaunch wecar teleop.launch`
  - `$ roscd wecar/map`
  - `$ rosrun map_server map_server "FILENAME.YAML"`
  - `$ roslaunch particle_filter localize.launch`





# WeGo Robotics

**Tel.** 031 – 229 – 3553

**Fax.** 031 – 229 – 3554



**제품 문의:** [go.sales@wego-robotics.com](mailto:go.sales@wego-robotics.com)

**기술 문의:** [go.support@wego-robotics.com](mailto:go.support@wego-robotics.com)